

ROS 2 Odometry Variable Fetcher

This notebook uses a helper function to subscribe to the `/odom` topic and fetch one value for each major odometry variable.

Ensure your ROS 2 system is running and publishing to `/odom` before executing the cells.

```
In [ ]: # Step 1: Import the helper function from script
        from get_odom_variable import get_odom_variable
```

Step 2: Fetch Odometry Values

This will get a **single value** from the odometry message for each key variable.

```
In [ ]: # Position (meters)
        pos_x = get_odom_variable('pose.pose.position.x')
        pos_y = get_odom_variable('pose.pose.position.y')
        pos_z = get_odom_variable('pose.pose.position.z')

        # Orientation (quaternion)
        orient_x = get_odom_variable('pose.pose.orientation.x')
        orient_y = get_odom_variable('pose.pose.orientation.y')
        orient_z = get_odom_variable('pose.pose.orientation.z')
        orient_w = get_odom_variable('pose.pose.orientation.w')

        # Linear velocity (m/s)
        lin_x = get_odom_variable('twist.twist.linear.x')
        lin_y = get_odom_variable('twist.twist.linear.y')
        lin_z = get_odom_variable('twist.twist.linear.z')

        # Angular velocity (rad/s)
        ang_x = get_odom_variable('twist.twist.angular.x')
        ang_y = get_odom_variable('twist.twist.angular.y')
        ang_z = get_odom_variable('twist.twist.angular.z')
```

Step 3: Display the Results

```
In [ ]: print(f"\n Position:")
        print(f"   x = {pos_x:.3f} m, y = {pos_y:.3f} m, z = {pos_z:.3f} m")

        print(f"\n Orientation (quaternion):")
        print(f"   x = {orient_x:.3f}, y = {orient_y:.3f}, z = {orient_z:.3f}, w = {orient_w:.3f}")
```

```

print(f"\n Linear Velocity:")
print(f"   x = {lin_x:.3f} m/s, y = {lin_y:.3f} m/s, z = {lin_z:.3f} m/s")

print(f"\n Angular Velocity:")
print(f"   x = {ang_x:.3f} rad/s, y = {ang_y:.3f} rad/s, z = {ang_z:.3f} rad/s")

```

Step 4: Collect Variables Over Time

This cell collects `position.x` and `angular.z` over time and saves the data to a CSV file.

```

In [ ]: import pandas as pd
import time

# Collect N samples at interval (seconds)
N = 10 # number of samples
interval = 1.0 # seconds between samples

log_data = []

for i in range(N):
    pos_x = get_odom_variable('pose.pose.position.x')
    ang_z = get_odom_variable('twist.twist.angular.z')
    timestamp = time.time()
    log_data.append({'time': timestamp, 'pos_x_m': pos_x, 'ang_z_rad_s': ang_z})
    print(f"[{i+1}/{N}] Logged: pos_x = {pos_x:.3f}, ang_z = {ang_z:.3f}")
    time.sleep(interval)

df = pd.DataFrame(log_data)

```

Step 5: Save Data to CSV

```

In [ ]: df.to_csv("odom_log.csv", index=False)
print(" Saved to odom_log.csv")
df.head()

```